

MatPar

```
#- $Id: //tcad/support/main/examples/opto/solarcell/iiiv/sc-iiiv-dj-
epi/mpr_mpr.cmd#2 $
#setdep @previous@
#-----
# global user variables for e.g. material processing
set temp 300

#-----
# load the layer variables. The epi tool saves the layer data typically in
# ./n@node|epi@_epi.tcl layer data can be accessed through
source "@pwd@/@epitcl@"

#-----
# configure mpr
# specify Global parameter database default is $STREPODIR/pardb
# set mprGlobalParDb ~/db/myrepository

# configure local parameter directory
# set mprLocalParDir ./par

# Specify main parameter file name
# set mprMainParameterFile n@node@_mpr.par

# If set to 1, do not print any lines starting with # in the preprocessed files
# set mprNoComments 0

# Set directory where the preprocessed parameter files are stored
# set mprPpParDir ./npar

# choose the preprocessor used by mpr internal | spp
# set mprPreprocessor internal
```

SDE

```
;;-----
;;$Id: //tcad/support/main/examples/opto/solarcell/iiiv/sc-iiiv-dj-
epi/sde_dvs.cmd#4 $
;;-----
;; Create the layer stack,
(sdeepi:create-layerstack "@epicsv@")
;;-----
;; Create the tcl file:
(sdeepi:tcl "@epicsv@" "@epitcl@")
;;-----
;; Create the scm file:
(sdeepi:scm "@epicsv@" "@episcm@")
;;-----
(display " Reading in epi layer system") (newline)
(load "@episcm@")
;;-----
(display " Geometric variables") (newline)
(define wfront @wfront@)
(define dmgf 0.107)
```

```

(define dtiox 0.065)
(define dtdmetal 0.001)
;;-----
(display "  Refinements variables") (newline)
(define myRefOptScale 1.2)
(define myRefOptYmin 0.001)
(define myRefOptDepth 2)
(define myRefGlobalX 50)
(define myRefGlobalY 1.5)
(define myRefFrontContactOffset 2)
(define myRefFrontContactDepth 0.3)
(define myRefFrontContactX 5)
;;-----
(display "  other layer variables") (newline)
;; extract tunneldiode doping level to create component cells
(define Ntdn (abs @Ntdn@))
(define Ntdp (abs @Ntdp@))

;;-----
(display "Modifying EPI") (newline)
;;-----
(display "  etching cap") (newline)
(sdeggeo:set-default-boolean "ABA")
;; In 1d remove cap completely
(define delme (sdeggeo:create-rectangle
  (position wfront Y0_cap 0 )
  (position Xmax Y1_cap 0 ) "xx" "xx"))
(entity:delete delme)
;;-----
(display "  deposit ARC") (newline)
(sdeggeo:create-rectangle
  (position wfront Y0_topfsf 0 )
  (position Xmax (- Y0_topfsf dtiox) 0 )
  "TiOx" "arc1")
(sdeggeo:create-rectangle
  (position wfront (- Y0_topfsf dtiox) 0 )
  (position Xmax (- Y0_topfsf dtiox dmf) 0 )
  "MgF" "arc2")

;;-----
(display "Add Contacts") (newline)
;;-----
(display "  top contact") (newline)
(sdeggeo:define-contact-set "cathode" 4 (color:rgb 1 0 0 ) "##" )
(sdeggeo:set-current-contact-set "cathode")
;; In 1d put cathod on top of fsf, in 2d on top of cap
(if (> wfront 0)
  (begin
    (define x (/ wfront 2))
    (define y Y0_cap)
  ) ;else
  (begin
    (define x (/ Xmax 2))
    (define y Y0_topfsf)
  ));endif
(sdeggeo:define-2d-contact (find-edge-id (position x y 0)) "cathode")
;;-----

```

```

(display " bottom contact") (newline)
(sdegeo:define-contact-set "anode" 4 (color:rgb 1 0 0 ) "##" )
(sdegeo:set-current-contact-set "anode")
(sdegeo:define-2d-contact (find-edge-id (position (/ Xmax 2) Ymax 0)) "anode")
(sde:refresh) ; to display contacts in gui mode

;;-----
(display "Creating Component") (newline)
(sdedr:define-constant-profile "ndop_component" "ArsenicActiveConcentration"
Ntdn)
(sdedr:define-constant-profile "pdop_component" "BoronActiveConcentration" Ntdp)
#if [string match "*topcell*" "@geo@"]
;-----
(display " topcell\n")
(sdedr:define-refinement-window "p_ref_component" "Rectangle"
(position Xmin Y0_tdn 0)
(position Xmax Ymax 0) )
(sdedr:define-constant-profile-placement "p_component" "pdop_component"
"p_ref_component" 0 "Replace")
#elif [string match "*bottomcell*" "@geo@"]
;-----
(display " bottomcell\n")
(sdedr:define-refinement-window "n_ref_component" "Rectangle"
(position Xmin Ytop 0)
(position Xmax Y1_tdp 0) )
(sdedr:define-constant-profile-placement "n_component" "ndop_component"
"n_ref_component" 0 "Replace")
#endif

;;-----
(display "Add Refinements") (newline)
;-----
(if (> wfront 0)
(begin
(display " global refinement") (newline)
(sdedr:define-refinement-window "global" "Rectangle"
(position Xmin Ymin 0)
(position Xmax Ymax 0) )
(sdedr:define-refinement-size "global"
myRefGlobalX myRefGlobalY 0
myRefGlobalX myRefGlobalY 0)
(sdedr:define-refinement-placement "frontContact" "frontContact"
"frontContact" )
));endif
;;-----
(display " optical refinement") (newline)
(sdedr:define-refinement-window "optics" "Rectangle"
(position wfront Y0_topfsf 0)
(position Xmax myRefOptDepth 0) )
(sdedr:define-multibox-size "optics" Xmax 10 Xmax myRefOptYmin 1 myRefOptScale )
(sdedr:define-multibox-placement "optics" "optics" "optics" )
;;-----
(if (> wfront 0)
(begin
(display " front contact refinement") (newline)
(sdedr:define-refinement-window "frontContact" "Rectangle"
(position Xmin Ymin 0)

```

```

        (position (+ Xmin wfront myRefFrontContactOffset) (+ Y0_topfsf
myRefFrontContactDepth) 0) )
        (sdedr:define-refinement-size "frontContact"
          (/ wfront myRefFrontContactX) 10 0
          (/ wfront myRefFrontContactX) 10 0 )
        (sdedr:define-refinement-placement "frontContact" "frontContact"
"frontContact" )
      ));endif

;;-----
(display "saving & meshing") (newline)
(sde:build-mesh "snmesh" "-a -y 1e6 -r 1e6" "n@node@_msh")
(display "... done.") (newline)

```

SDEVICE_DES

```

#setdep @previous@

*-----
* create bias spectrum.
* For IV cut of spectrum at wend.
* For EQE scale intensity for non-investigated cells
!(
set spectrum "@pwd@/par/spectra/@spectrum@"
set wcrossover 0.65 ;# bandedge wavelength of top cell in um
set wend 0.9 ;# end of spectrum in um
set sfactor 2.0 ;# scaling factor for the bias light of the non-investigated cell
spectrum range.
set signalIntensity 0.01 ;# intensity of the measurement light in W/cm^2
# read in spectrum

set fid [open $spectrum r]
set wilist {}
set headerlist {}
while { [gets $fid LINE] >= 0 } {
    set LINE [string trim $LINE]
    if {[string range $LINE 0 0] == "#" || [string length $LINE] == 0}
{continue}
    if {[regexp {[0-9\.eE\-\+]} [lindex $LINE 0]]} {
        lappend headerlist $LINE
        continue
    }
    set w [lindex $LINE 0]
    set i [lindex $LINE 1]
    if {$w <= $wend} {lappend wilist [list $w $i]}
}
close $fid
set wilist [lsort -real -index 0 $wilist]
set wstart [lindex $wilist 0 0]
set wend [lindex $wilist end 0]
set wsteps [llength $wilist]
# write out bias spectrum with reduced values for investigated cell
# transform wavelength list to time list [0..1]
set fid [open "pp@node@_spec.txt" w]
foreach h $headerlist { puts $fid $h }

```

```

set timelist {}
foreach wi $wilist {
    set w [lindex $wi 0]
    set i [lindex $wi 1]
    # apply sfactor to not investigate cell's spectrum
    if {[string match "*eqetop*" "@mode@" ] && $w >= $wcrossover || \
        [string match "*eqebot*" "@mode@" ] && $w <= $wcrossover} {
        set i [expr $i*$sfactor]
    }
    puts $fid "$w $i"
    lappend timelist [expr 1.*( $w-$wstart)/($wend-$wstart)]
}
close $fid
# put some info on the spectrum in the preprocessed command file
puts "* wavelength range: \[$wstart, $wend\] entries: $wsteps"
puts "* wavelength crossover: $wcrossover sfactor: $sfactor"
)!

*-----
***** Sourcing the @epitcl@ file for geometric parameters used for nonlocal mesh
#if ![file exists "@epitcl@"]
* Warning: File @epitcl@ does not exists yet. Run epi node first.
#exit
#endif
!(source @epitcl@)!

*-----
File {
    *-Input
    Grid=      "@tdr@"
    Parameter= "@mprpar@"
    #if "@spectrum@" != "_"
    * use spectrum from tcl pp above
    IlluminationSpectrum= "pp@node@_spec.txt"
    #endif
    *-Output
    Output  = "@log@"
    Current= "@plot@"
    Plot=    "@tdrdat@"
}

*-----
Electrode {
    { Name= "anode"  Voltage= 0.0 }
    { Name= "cathode" Voltage= 0.0}
}

*-----
Plot {
    *- Doping Profiles
    DopingConcentration DonorConcentration AcceptorConcentration
    *- Band structure
    BandGap BandGapNarrowing ElectronAffinity
    ConductionBandEnergy ValenceBandEnergy
    eQuasiFermiEnergy hQuasiFermiEnergy
    *- Carrier Densities:
    eDensity hDensity

```

```

EffectiveIntrinsicDensity IntrinsicDensity
*- Fields, Potentials and Charge distributions
ElectricField/Vector
Potential
SpaceCharge
*- Currents
Current/Vector eCurrent/Vector hCurrent/Vector
CurrentPotential * for visualizing current flow lines
eMobility hMobility
*- Generation/Recombination
SRHRecombination AugerRecombination TotalRecombination SurfaceRecombination
RadiativeRecombination eLifeTime hLifeTime
#if "@spectrum@" != "_"
*- Optical Generation
ComplexRefractiveIndex QuantumYield
OpticalIntensity AbsorbedPhotonDensity OpticalGeneration
#endif
#if [string match "*nlm*" "@model@"]
eBarrierTunneling hBarrierTunneling NonLocal
#endif
}

*-----
CurrentPlot {
  #if [string match "*eqe*" "@mode@"]
  ModelParameter="Wavelength"
  #endif
  #if "@spectrum@" != "_"
  AbsorbedPhotonDensity(Integrate(Semiconductor))
  OpticalGeneration(Integrate(Semiconductor))
  OpticalGeneration(Integrate(Material="GaInP"))
  OpticalGeneration(Integrate(Material="GaAs"))
  #endif
  SRH(Integrate(Semiconductor))
  Auger(Integrate(Semiconductor))
  Radiative(Integrate(Semiconductor))
}

*-----
* Global physics
Physics {
  AreaFactor= @<lell/wtot>@ * to get current in mA/cm^2
  Fermi
  HeteroInterface
  ThermionicEmission
  #if [string match "*nlm*" "@model@"]
    eBarrierTunneling "NLM"(
      Band2Band
      TwoBand
    )
    hBarrierTunneling "NLM"(
      Band2Band
      TwoBand
    )
  #endif
  #if "@spectrum@" != "_"
  Optics (

```

```

ComplexRefractiveIndex(WavelengthDep(Real Imag))
OpticalGeneration(
    QuantumYield(StepFunction(EffectiveBandgap)) * generated carriers/photon,
default: 1
    ComputeFromSpectrum(
        * for the floating tunneljunction we need to find the initial solution in
transient
        #if [string match "*transient*" "@model@"]
        TimeDependence(
            WaveTime = (1, 1000)
            WaveTSlope =1
        )
        scaling = 1
        #else
        scaling = @suns@
        #endif
    )
    * for ege we need an additional monochromatic measurement source
    #if [string match "*ege*" "@mode@"]
    ComputeFromMonochromaticSource()
    #endif
)
Excitation (
    Theta= 0          * Normal incidence
    Polarization= 0.5  * Unpolarized light
    #if [string match "*ege*" "@mode@"]
    Wavelength = !(puts -nonewline $wstart)!
    Intensity = 0
    #endif
    Window (
        Line (
            * for 1D we have no front metalization x=[0..1]
            #if @wfront@ == 0
            X1=0
            #else
            X1= @<wfront+1.e-6>@
            #endif
            X2= @wtot@
        ) *end Line
    ) * end window
) * end Excitation
OpticalSolver (
    TMM (
        IntensityPattern= StandingWave
        LayerStackExtraction (
            * assume infinite thick substrate at the rear
            Medium (
                Location= bottom
                Material= "GaAs"
            )
        ) *end LayerStackExtraction
    ) *end TMM
) * end OpticalSolver
) * end optics
#endif
}

```

```

*-----
* Regionwise specific physics
Physics (material="AlInP") {
    EffectiveIntrinsicDensity(NoBandgapNarrowing)
    Mobility()
    Recombination( Radiative )
}

Physics (material="GaInP") {
    EffectiveIntrinsicDensity(NoBandgapNarrowing)
    Mobility()
    Recombination( Radiative )
}

Physics (Region="topbase") {
    EffectiveIntrinsicDensity(NoBandgapNarrowing)
    Mobility()
    Recombination( Radiative )
    #if "@spectrum@" != " _ "
    * for thick regions avoid interpolation errors due to non resolved standing
wave patterns
    Optics(OpticalSolver(TMM(IntensityPattern = Envelope)))
    #endif
}

Physics (material="GaAs") {
    Mobility(DopingDependence)
    Recombination(
        SRH Auger Radiative
    )
    EffectiveIntrinsicDensity(
        BandgapNarrowing( TableBGN )
    )
}

Physics (Region="botbase") {
    Mobility(DopingDependence)
    Recombination( SRH Auger Radiative )
    EffectiveIntrinsicDensity(
        BandgapNarrowing( TableBGN )
    )
    #if "@spectrum@" != " _ "
    * for thick regions avoid interpolation errors due to non resolved standing
wave patterns
    Optics(OpticalSolver(TMM(IntensityPattern = Envelope)))
    #endif
}

*-----
Math{
    Iterations= 16
    Extrapolate
    RhSMin=1e-15
    RHsMax=1e15
    RHSFactor=1e20
    RelErrControl
    ErReff(electron)= 100
}

```



```

ErReff(hole)= 100
#if [string match "*extended*" "@model@"]
* for floating regions use extended precision for convergence
ExtendedPrecision # (128) in case of convergence issues
Digits= 15
#else
Digits= 6
#endif
DirectCurrentComputation
ExitOnFailure
-ExitOnUnknownParameterRegion
#if "@spectrum@" != "_"
* for IV stop voltage ramp after Voc
BreakCriteria {
    Current (Contact= "cathode" minval= -1e-3)
}
#endif
#if [string match "*nlm*" "@model@"]
Nonlocal "NLM" (
    RegionInterface="tdn/tdp"
    * get length for non local mesh from epi layer information
    Length = !(puts -newline [expr ($epi(region,tdn,thickness)-0.5e-3)*1e-4])!
# [cm] distance to anchor point
    Permeation = !( puts -newline [expr ($epi(region,tdp,thickness)-0.5e-3)*1e-
4])!
    * non local mesh created in both directions, one is enough.
    -Transparent(region="tdp")
)
#endif
}

*-----
Solve {
*-----
    #if "@mode@" == "Eg"
    * for band diagram plots
    Poisson
    Plot (FilePrefix= "n@node@_Poisson")
    *-----
    #else
    * find initial solution
    NewCurrentPrefix= "tmp_"
    Poisson
    #if [string match "*transient*" "@model@"]
    * transient to switch on light and for have floating region converge ...
    Transient(
        initialtime=0 finaltime= 1 initialstep=1e-2 minstep=1e-9 maxstep= 1
    ) {
        Coupled {Poisson Electron Hole }
    }
    * further ramp light to high concentration
    Quasistationary (
        DoZero
        InitialStep = @<10./suns>@ MaxStep = 1 Minstep = 1e-12 Increment = 5
        Decrement = 5
        Goal { ModelParameter="Scaling" value=@suns@} * ramp up light
    ) {

```

```

        Coupled { Poisson electron Hole }
    }
#endif
NewCurrentPrefix= ""

*-----
#if "@mode@" == "jsc"
* short circuit current only
Coupled (Iterations= 100){ Poisson Electron Hole }
Plot (FilePrefix= "n@node@_jsc")
*-----
#elif "@mode@" == "iv"
* light IV curve
Coupled (Iterations= 100){ Poisson Electron Hole }
Plot (FilePrefix= "n@node@_jsc")
* define parameters for voltage ramps depending on cell type
#if [string match "*topcell*" "@geo@"]
#define _V1 1.0
#define _di1 0.5
#define _dm1 1.0
#define _V2 1.5
#define _di2 0.05
#define _dm2 0.05
#elif [string match "*bottomcell*" "@geo@"]
#define _V1 0.6
#define _di1 0.5
#define _dm1 1.0
#define _V2 1.2
#define _di2 0.05
#define _dm2 0.05
#elif [string match "*tandemcell*" "@geo@"]
#define _V1 1.9
#define _di1 0.5
#define _dm1 1.0
#define _V2 2.7
#define _di2 0.05
#define _dm2 0.05
#endif
* quick coarse ramp right before mpp
Quasistationary (
    InitialStep= _di1 MinStep= 5e-4 MaxStep= _dm1 Increment= 2 Decrement= 2
    #Plot {Range= (0 1) Intervals= 3}
    Goal { Name="anode" Voltage= _V1 }
){ Coupled { Poisson Hole Electron }
    #Plot(FilePrefix= "n@node@_mpp" When(Contact = "anode" voltage = 0.9 ))
}
Plot(FilePrefix= "n@node@_mpp" )
* finer ramp until Voc
Quasistationary (
    InitialStep= _di2 MinStep= 0.001 MaxStep= _dm2 Increment= 2 Decrement= 2
    #Plot {Range= (0 1) Intervals= 3}
    Goal { Name="anode" Voltage= _V2 }
){
    Coupled { Poisson Hole Electron }
    #Plot(FilePrefix= "n@node@_0.8V" When(Contact = "anode" voltage = 0.8 ))
}

```

```

*-----
#elif [string match "*eqe*" "@mode@"]
* get bias current without monochromatic light, monochromatic intensity=0 here
NewCurrentPrefix = "bias_"
Coupled {Poisson Electron Hole}
* switch on monochromatic light
NewCurrentPrefix = ""
Quasistationary (
  InitialStep = 1  MaxStep = 1  Minstep = 1e-5
  Goal { modelParameter="Intensity" value=!(puts -nonewline $signalIntensity)! }
}
) { Coupled (Iterations=30) {Poisson Electron Hole} }
# Plot (FilePrefix="n@node@_bias")
* ramp through wavelength list of spectrum
Quasistationary (
  InitialStep = 1  MaxStep = 1  Minstep = 0.0001
  Goal { modelParameter="Wavelength" value=!(puts -nonewline $wend)! }
) {
  Coupled(Iterations=100) {Poisson Electron Hole}
  # Plot(FilePrefix=n@node@ NoOverwrite)
  CurrentPlot(Time=!(puts -nonewline "[join [lrange $timelist 1 end]
"\;"]")!))
}
#endif
System("rm -f tmp*") *remove the plots we dont need anymore
#endif
}

```